

Driver Installer Guide

Version C4 2013

1 Installing new drivers

1. Launch Driver Installer located in the Gamanet folder.




Figure 1 - Starting Driver Installer

2. Viewing the list of drivers

- a. If the server has internet access, the list of latest versions of released drivers will be loaded automatically and they can be installed immediately as per point 3.




Figure 2 - Automatic loading of available drivers from the internet

- b. If internet access is not available or if you need to load a driver from a local folder, click **Load folder** and select the folder with saved drivers.




Figure 3 - "No internet access" message

Select the folder with the drivers and click **OK**.




Figure 4 - Loading drivers from a local folder

3. Drivers and their properties appear on the list:

- Driver: driver name
- Version: driver version
- Category: assigning the driver to various categories depends on the usage type
- Producer: name of the company that developed the driver
-  means that the driver is certified.

4. Find the required driver in the list and click into a small square ☐ to select it.

Tip

Entering a filtering condition in the search field can narrow the driver list and help you find the required driver faster. You can filter by all driver parameters.




Figure 5 - Filtering the list of drivers

5. Click **Install selected** to launch the installation of the specified driver. The system will prompt you to confirm to stop the *Device Manager* service, which is required during driver installation.




Figure 6 - Stopping the Device Manager service

Warning:

After stopping the *Device Manager*, all communication with all devices will halt.

5. A successful driver installation is signalled by a dialog box.




Figure 7 - "Driver installation successful" message

7. The C4 client device tree enables you to add devices with installed drivers.




Figure 8 - Adding new devices

Warning:

If no drivers are installed, the client application will not display the option of adding a new device.

2 Updating existing drivers

If there are drivers already installed in the system with an update available, you can update them using the Driver Installer.

1. Load the folder with the updated drivers.




Figure 9 - Updating installed drivers

2. If a previous version of a driver is already installed and a newer version is available, the new driver appears at the top of the list. The driver name is followed by the version that is available to install and the installed version is enclosed in brackets.
3. Click the small square to select the updated driver ☐ and then click **Update selected**. This will initiate an update of the selected drivers.

Tip:

Clicking **Update all** updates all installed drivers for which an update is available.

Warning:

After installing or updating a driver, it is necessary to close and start again (not restart) C4 client application, in order to download driver definitions to the client computer.

3 Downloading and saving a driver

If a driver needs to be saved to a local computer without installation, follow the steps below.

1. Select the required driver.
2. Click **Download selected**.
3. Select the folder you want to save the driver to.




Figure 10 - Selecting a folder for saving

4. A successful driver download is signaled by a dialog box.




Figure 11 - "Saved successfully" message